

Quartus Setup Issues


Common - last updated 9/6/17

Quartus Setup Issues


- ModelSim Path not set
- No USB Blaster

Quartus Setup Issues

- ModelSim Path not set




- Go to **Tools** → **Options** → **EDA Tool Options**
 - Select the ... after **Modelsim Altera**



Quartus Setup Issues


- ModelSim Path not set
 - Traverse to `C:\intelFPGA_lite\18.0\modelsim_ase`
 - Highlight the `win32aloem` file and select `Select Folder`



ModelSim		...
QuestaSim		...
ModelSim-Altera	C:\intelFPGA_lite\18.0\modelsim_ase\win32aloem	...


Quartus Setup Issues

- No USB Blaster when trying to program



Quartus Setup Issues

- No USB Blaster when trying to program
 - Plug in the board
 - In Windows, open the Device Manager
 - Find the USB Blaster device



Yours may be under a different tab

Quartus Setup Issues

- No USB Blaster when trying to program
 - Right click on the **Altera USB-Blaster** and select **Update Driver**
 - Select **Browse my computer ...**
 - Browse to **C:\intelFPGA-lite**
 - Check the **Include subfolders** box

